



Dell EMC

DES-4121 Exam

DES-4121 Implementation Engineer PowerEdge

Thank you for Downloading DES-4121 exam PDF Demo

You can Buy Latest DES-4121 Full Version Download

<https://www.certkillers.net/Exam/DES-4121>

<https://www.certkillers.net>

Version: 8.0

Question: 1

A technician needs to install the OS on a server remotely using iDRAC. What is the minimum iDRAC license required to perform this task?

- A. Express
- B. Enterprise
- C. Basic
- D. Baseboard Management Controller

Answer: B

Reference <https://community.spiceworks.com/topic/514389-dell-idrac-licensing>

Question: 2

A technician needs to replace a server component with orange tabs/releases. Which set of paired steps should the technician take to complete this task?

- A. Power off the server
Apply anti- static procedures
- B. Remove power cables
Cold swap the component
- C. Cold swap the component
Apply anti-static procedures
- D. Hot swap the component
Apply anti -static procedures

Answer: D

Reference

https://www.sos.state.co.us/pubs/elections/VotingSystems/DVS-DemocracySuite/documentation/Dell_Poweredge_R630_Owner_Manual.pdf (84)

Question: 3

A technician creates two virtual disks and assigns a dedicated hot spare to each virtual disk. They also create a global hot spare. A drive fails on the second virtual disk what is the result?

- A. Dedicated hot spare for the virtual disk replaces the failed drive.
- B. Global hot spare replaces the failed drive
- C. Copyback operation occurs between the failed drive and the dedicated hot spare

D. Copyback operation occurs between the tailed drive and the global hot spare

Answer: B

Refe

<https://www.dell.com/support/article/pk/en/pkbsd1/sln305775/dell-poweredge-how-to-assign-a-hard-drive-in-global-hot-spare-?lang=en>

Question: 4

What can a technician do to ensure that no malicious code can be introduced into any of the servers through physical access?

- A. Set USB 3.0 to disabled
- B. Set Secure Boot Policy to enabled
- C. Set User Accessible Ports to disabled
- D. Set UEFI Variable Access to disabled

Answer: C

Since normal iDRAC credentials are used for logging in, iDRAC Direct works as a secure crash cart with the additional advantage of extensive hardware management and service diagnostics. This can be an attractive option for securing physical access to the server in remote locations (host USB ports and VGA outputs can be disabled in this case)

Question: 5

A technician is installing a new server and is not getting any link lights on the iDRAC management port. They have verified that the cable and switch port are working. What could be causing this issue?

- A. iDRAC has an Express license
- B. IP has not been set the Lifecycle Controller
- C. iDRAC has been disabled in the lifecycle Controller
- D. iDRAC firmware update is currently in progress

Answer: D

Thank You for trying DES-4121 PDF Demo

To Buy Latest DES-4121 Full Version Download visit link below

<https://www.certkillers.net/Exam/DES-4121>

Start Your DES-4121 Preparation

[Limited Time Offer] Use Coupon “CKNET” for Further discount on your purchase. Test your DES-4121 preparation with actual exam questions.

<https://www.certkillers.net>